

---

# Profiles

---

Profiles provide the option to differentiate settings used by Smart Clients.

This functionality can be used to deal with Smart Clients connecting to the server from behind different types of firewalls and/or proxies, which would require different settings.

Each profile has a name and by adding the name of the profile to the URL that is used to launch the Smart Client, settings provided in the Profile overrule the default settings and/or settings provided in the URL itself.

## Deeplink into specific solution using a named Profile

```
{serverUrl}/servoy-client/{profileName}/{solutionName}.jnlp
```

The profile part of the URL is only relevant for the launch of the Smart Client. When deeplinking into running Smart Clients the profile can be omitted from the deeplink URL. For more info on all possible options for Smart Clients URL's, see [Starting Smart Clients](#).

A profile can contain one or more settings. There are three basic types of settings:

1. Deeplink settings
2. Configuration settings
3. Servoy settings

All these settings will be saved in the server's `servoy.properties` file.

### Deeplink Settings

Through profiles it's possible to specify startup arguments and/or a deeplink method, by adding one of the following properties:

- `solution={solutionName}`
- `method={globalMethodName}`
- `argument={someValue}`
- `{someParam}={someValue}`

For the solution, method and argument settings, it's also possible to use the short syntax (resp. `s`, `m` and `a`).

### Configuration Settings

Configuration properties are properties that start with 'system.property.'. Any property that starts with this will be sent to the launched Smart Client. This can be either standard Java system properties or Servoy specific system properties, including Tunnel configuration properties.

#### *Java system properties*

Any system property that Java has can be added to the Profile. Whether or not the property has any relevancy depends on the property.

#### *Servoy configuration properties*

There are two Servoy specific system properties that can be used within a Profile:

- `system.property.servoy.usejaas`: include and set to true for Kerberos support
- `system.property.SocketFactory.tunnelConnectionMode`: specifies the tunnel connection mode, either 'http' or 'socket'.  
For this setting to have effect, the `SocketFactory.tunnelConnectionMode` setting under Network Settings on the Admin page needs to be set to 'http&socket'

#### *Tunnel configuration properties*

The Tunnel has an extensive set of configuration options to allow optimal operation for any combination of firewalls and proxies. More information on the configuration options for the tunnel can be found at [Advanced HTTP Tunnel Configuration](#).

### Servoy Settings

Servoy properties are properties that start with 'servoy.' like 'servoy.maxClientHeap' or 'servoy.branding'.

All Servoy properties that are related to the Smart Client can be added to the Profile.