

# Running the server as a service

The Servoy Application Server comes bundles with an Java Service Wrapper component, to facilitate the automatic launch of the Servoy Application Server when the server on which the Servoy Application Server is installed is started or rebooted.

⚠ The Java Service Wrapper does not start the required databases as the databases are not part of the Servoy Application Server, could be running on a completely different machine and different brands of databases have different mechanisms to starting. For more information on running the bundled PostgreSQL as a service, see the [PostgreSQL Primer](#) tutorial.

When running the Servoy Application Server and the database on the same Windows machine, both as a Windows Service, then a dependency can be configured between the different Windows services. See [Configuring Windows Service dependencies](#) for more info.

## In This Chapter

- [Supported platforms](#)
- [Installation](#)
- [Additional configuration](#)
  - [Changing configuration on Windows](#)
  - [Configuring the Windows Service to automatically start on reboot of the machine](#)
  - [Configuring Windows Service dependencies](#)
  - [Memory Setting](#)
  - [Running multiple Servoy Application Servers as a Service on a single machine](#)
  - [Additional configurations](#)
  - [More info on the Java Service Wrapper component](#)

## Supported platforms

While the Java Service Wrapper used by Servoy supports virtually all platforms on which a Java Virtual Machine is available (also required to run the Servoy Application Server), in Servoy up to Servoy 6 it's only available on Windows.

For more info on the Java service Wrapper see the paragraph [More info on the Java Service Wrapper component](#) below.

The Java service Wrapper component will create a Windows Service on the Windows platform.

## Installation

The Java Service Wrapper is an optional component that needs to be checked in the Servoy All-In-One installer, see [Running the All-In-One Installer](#) (The *Application Server Service* option).

When checked during the installation, an extra *service* directory is created in the *../application\_server/* directory. This directory contains, among others, the configuration file for the service, called *wrapper.conf*.

The Windows Service will be automatically installed when the All-In-One installer has finished.

## Additional configuration

The configuration of the Java Service Wrapper is done through the file *wrapper.conf* located in *../application\_server/service*.

### [Changing configuration on Windows](#)

When changing the value of any any *wrapper.ntservice.\** property, the Service needs to be uninstalled first and reinstalled after the changes have been made.

Uninstalling the Windows Service can be done using the following command:

```
wrapper -r wrapper.conf
```

(Re)installing the Windows Service can be done using the following command:

```
wrapper -i wrapper.conf
```

### [Configuring the Windows Service to automatically start on reboot of the machine](#)

By default the Windows Service is configured to be started manually. This can be changed by setting the *wrapper.ntservice.starttype* property to *AUTO\_START*.

### [Configuring Windows Service dependencies](#)

The Java Service Wrapper does NOT start the database, as in production environments the database could be installed on a different machine or is maintained by a DBA.

If the database is running on the same machine as a Windows Service as well, it is possible to configure a dependency to it in the Java Service Wrapper configuration. The dependency can be set by adding the name of the Windows Service for the database on which the Servoy Application Service depends as the *wrapper.ntservice.dependency.x property*. The "x" at the end of the property name needs to be a sequential number, starting with 1, for each dependency.

### Memory Setting

When the Servoy Application server is started as a service through the Java Service Wrapper, the assignment of memory goes through the configuration of the wrapper in *wrapper.conf*, instead of through *servoy\_server.bat*.

Below the mapping for the three relevant memory settings and their equivalent in the *wrapper.conf*:

- Initial Java Heap Size > *wrapper.java.initmemory=...*
- Maximum Java Heap Size > *wrapper.java.maxmemory=...*
- Maximum Java Perm Size > *wrapper.java.additional.4=-XX:MaxPermSize=...*

For more information on the the meaning of these settings and their suggested values, see [Memory Management](#).

### Running multiple Servoy Application Servers as a Service on a single machine

When running multiple Servoy Application Servers as a Service on a single machine, some configuration adjustments are required to not let the different services influence eachother.

The following property requires a unique value:

- *wrapper.ntservice.name* (default *ServoyService*)

On Windows the *wrapper.ntservice.displayname* and *wrapper.ntservice.description* could be modified to further distinguish the different Windows Services from each other. Note that these two settings are just for display purposes in the Services overview in Windows and do not affect the actual operation of the services.

The *wrapper.port* value does not have to be unique, because the Java Service Wrapper automatically looks for a free port if the specified port is already taken.

### Additional configurations

The Java Service Wrapper has extensive configuration options. The most fundamental settings have been discussed in this chapter already. In this paragraph some more advanced settings are detailed.

#### Perform custom action on OutOfMemory exceptions

Java process need to be explicitly told how much memory they are allowed to use. In case the process requires more memory than it's allowed to use based on the configuration, Java will throw *OutOfMemory* exceptions. When this happens, the state of the process becomes unreliable, as some vital business logic might not have been executed. Java only has limited options to take action when *OutOfMemory* exceptions occur.

The Java Service Wrapper however support a monitoring feature that is capable of taking action in case *OutOfMemory* exceptions occur. The following snippet of configuration will perform a thread dump and then a restart of the Servoy Application Server.

```
wrapper.filter.trigger.1=Exception in thread "*" java.lang.OutOfMemoryError
wrapper.filter.action.1=NONE

wrapper.filter.trigger.2=Exception in thread "*" java.lang.OutOfMemoryError
wrapper.filter.allow_wildcards.2=TRUE
wrapper.filter.action.2=DUMP,RESTART
wrapper.filter.message.2=The JVM has run out of memory.
```

### More info on the Java Service Wrapper component

The Java Service Wrapper is a bundled third party component also called [Java Service Wrapper Standard](#) by [Tanuki Software](#). For indepth documentation have a look [here](#).

The component is licensed by Servoy to be bundled and used in combination with the Servoy Application Server only. It's not allowed to use the component outside the context of the Servoy Application Server.