

RuntimelImageMedia

ImageMedia fields are fields that can display images.

The user can, depending on the field state (enabled/readonly) get/set of update the contents of the field.

When the user sets/uploads the content of the field, Servoy has special logic that retrieves the filename and mimetype of the uploaded file and stores those in dataproviders that follow the following naming convention:

- filename: DataProviderID (of the ImageMedia field) + "_filename"
- mimetype: DataProviderID (of the ImageMedia field) + "_mimetype"

Property Summary

String	#bgcolor	Gets or sets the background color of a field.
String	#border	Gets or sets the border attribute(s) of a specified element.
Boolean	#enabled	Gets or sets the enabled state of a specified field, also known as "grayed".
String	#fgcolor	Gets or sets the foreground color of a field.
String	#font	Sets the font name, style, and size of an element.
Boolean	#readOnly	Gets or sets the editable/read-only state of a field; true - read-only; false - editable; ! - the editable/read-only state is inverted (the opposite).
String	#titleText	Gets or sets the title text.
String	#toolTipText	Gets or sets the tool tip text of an element; text displays when the mouse cursor hovers over an element.
Boolean	#transparent	Gets or sets the transparency of an element; true - transparent; false - not transparent.
Boolean	#visible	Gets or sets the visibility of an element; true - visible; false - not visible; ! - the visibility state is inverted (the opposite).

Method Summary

Number	#getAbsoluteFormLocationY()	Returns the absolute form (designed) Y location.
Object	#getClientProperty(key)	Gets the specified client property for the element based on a key.
String	#getDataProviderID()	Get the data provider this UI element (display) is showing.
String	#getElementType()	Returns the type of a specified element.
Number	#getHeight()	Returns the height of the current element.
Number	#getLocationX()	Returns the x location of the current element.
Number	#getLocationY()	Returns the y location of the current element.
String	#getName()	Returns the name of an element.
Number	#getScrollX()	Returns the x scroll location of the current portal or specified portal - only for a portal where the height of the portal is greater than the height of the portal field(s).
Number	#getScrollY()	Returns the y scroll location of the current portal or specified portal - only for a portal where the height of the portal is greater than the height of the portal field(s).
Number	#getWidth()	Returns the width of the current element.
Boolean	#isEditable()	Gets the editable/read-only state of a field; true - editable; false - read-only; ! - the editable/read-only state is inverted (the opposite).
void	#putClientProperty(key, value)	Sets the value for the specified element client property key.
void	#setLocation(x, y)	Sets the location of an element.
void	#setScroll(x, y)	Sets the scroll location of a portal.
void	#setSize(width, height)	Sets the size of the field.

Property Details

bgcolor

Gets or sets the background color of a field. The color has to be set using the hexadecimal RGB value as used in HTML.

Returns

String

Sample

```
//sets the background color of the field  
forms.customer.elements.customer_id.bgcolor = "#FFFFFF";  
//gets the background color of the field  
var c = forms.customer.elements.customer_id.bgcolor;
```

border

Gets or sets the border attribute(s) of a specified element.

The border attributes:

borderType - EmptyBorder, EtchedBorder, BevelBorder, LineBorder, TitleBorder, MatteBorder, SpecialMatteBorder.

size - (numeric value) for: bottom, left, right, top.

color - (hexadecimal value) for: bottom, left, right, top.

dash pattern - (numeric value) for selected side(s).

rounding radius - (numeric value) for selected side(s).

NOTE: Use the same value(s) and order of attribute(s) from the element design time property "borderType".

Parameters

spec – the border attributes

Returns

String

Sample

```
//sets the border type to "LineBorder"  
//sets a 1 px line width for the bottom and left side of the border  
//sets the hexadecimal color of the border to "#ccffcc"  
var b = forms.customer.elements.customer_id.setBorder('LineBorder',1,#ccffcc');
```

enabled

Gets or sets the enabled state of a specified field, also known as "grayed".

true - enabled; false - not enabled; ! - the enabled state is inverted (the opposite).

NOTE: A disabled element cannot be selected by clicking the element (or by pressing the TAB key even if this option is supported by the operating system).

NOTE: A label or button element will not disable if the "displayType" design time property for a field is set to HTML_AREA.

NOTE: The disabled "grayed" color is dependent on the LAF set in the Servoy Client Application Preferences. For more information see Preferences: Look And Feel in the Servoy Developer User's Guide.

Returns

Boolean

Sample

```
//gets the enabled state of the field  
var currState = forms.customer.elements.customer_id.enabled;  
  
//sets the enabled state of the field  
forms.customer.elements.customer_id.enabled = !currentState;
```

`fgcolor`

Gets or sets the foreground color of a field. The color has to be set using the hexadecimal RGB value as used in HTML.

Returns

`String`

Sample

```
//sets the foreground color of the field  
forms.customer.elements.customer_id.fgcolor = "#000000";  
  
//gets the foreground color of the field  
var c = forms.customer.elements.customer_id.fgcolor;
```

`font`

Sets the font name, style, and size of an element.

font name - the name of the font family.

style - the type of the font. (plain = 0; bold = 1; italic = 2; bold-italic = 3).

size - the size of the font (in points).

Parameters

spec – the font name, style, size

Returns

`String`

Sample

```
forms.customer.elements.customer_id.setFont('Tahoma',1,11');
```

`readOnly`

Gets or sets the editable/read-only state of a field; true - read-only; false - editable; ! - the editable/read-only state is inverted (the opposite).

NOTE: A field set as read-only can be selected by clicking (or pressing the TAB key if this option is supported by the operating system) and the field data can be copied.

Returns

`Boolean`

Sample

```
//gets the editable/read-only state of the field  
var currentState = forms.customer.elements.customer_id.readOnly;  
  
//sets the editable/read-only state of the field  
forms.customer.elements.customer_id.readOnly = !currentState;
```

`titleText`

Gets or sets the title text.

Returns

`String`

Sample

```
var titleText = forms.customer.elements.customer_id.titleText;
```

toolTipText

Gets or sets the tool tip text of an element; text displays when the mouse cursor hovers over an element.

NOTE: HTML should be used for multi-line tooltips; you can also use any valid HTML tags to format tooltip text.

Returns

String

Sample

```
//gets the tooltip text of the element
var toolTip = forms.customer.elements.customer_id.toolTipText;

//sets the tooltip text of the element
forms.customer.elements.customer_id.toolTipText = "New tip";
forms.customer.elements.customer_id.toolTipText = "<html>This includes <b>bolded text</b> and <font color='blue'>BLUE</font> text as well.";
```

transparent

Gets or sets the transparency of an element; true - transparent; false - not transparent.

NOTE: transparency can be inverted using ! operator: elements.elementName.transparent = !elements.elementName.transparent;

NOTE: transparency will be mostly used for background color, a transparent element will receive the background of the element "beneath" it, a non transparent one will use its own background color

Returns

Boolean

Sample

```
//gets the transparency of the element
var currentState = forms.customer.elements.customer_id.transparent;

//sets the transparency of the element
forms.customer.elements.customer_id.transparent = !currentState;
```

visible

Gets or sets the visibility of an element; true - visible; false - not visible; ! - the visibility state is inverted (the opposite).

NOTE: The visibility of an element is not persistent; the state of visibility only applies to the current user in his/her current session.

Returns

Boolean

Sample

```
//sets the element as visible
forms.company.elements.faxBtn.visible = true;

//gets the visibility of the element
var currentState = forms.company.elements.faxBtn.visible;

//sets the element as not visible when the current state is visible
forms.company.elements.faxBtn.visible = !currentState;
```

Method Details

getAbsoluteFormLocationY

Number **getAbsoluteFormLocationY()**

Returns the absolute form (designed) Y location.

Returns

Number – The y location of the form in pixels.

Sample

```
var absolute_y = forms.customer.elements.customer_id.getAbsoluteFormLocationY();
```

getClientProperty

Object **getClientProperty(key)**

Gets the specified client property for the element based on a key.

NOTE: Depending on the operating system, a user interface property name may be available.

Parameters

{Object} key – user interface key (depends on operating system)

Returns

Object – The value of the property for specified key.

Sample

```
var property = forms.customer.elements.customer_id.getClientProperty('ToolTipText');
```

getDataProviderID**String** **getDataProviderID()**

Get the data provider this UI element (display) is showing.

Returns

String – The data provider as String.

Sample

```
forms.customer.elements.customer_id.getDataProviderID();
```

getElementType**String** **getElementType()**

Returns the type of a specified element.

Returns

String – The display type of the element as String.

Sample

```
var et = forms.customer.elements.customer_id.getElementType();
```

getHeight**Number** **getHeight()**

Returns the height of the current element.

NOTE: getHeight() can be used with getWidth() to set the size of an element using the setSize function. For example:

```
//returns the width (w) and height (h)  
var w = forms.company.elements.faxBtn.getWidth();  
var h = forms.company.elements.faxBtn.getHeight();
```

//sets the new size

```
forms.company.elements.faxBtn.setSize(w,h);
```

```
//sets the new size and adds 1 px to both the width and height  
forms.company.elements.faxBtn.setSize(w+1,h+1);
```

Returns

Number – The height of the element in pixels.

Sample

```
var ht = forms.customer.elements.customer_id.getHeight();
```

getLocationX**Number** **getLocationX()**

Returns the x location of the current element.

NOTE: getLocationX() can be used with getLocationY() to set the location of an element using the setLocation function. For Example:

```
//returns the X and Y coordinates  
var x = forms.company.elements.faxBtn.getLocationX();  
var y = forms.company.elements.faxBtn.getLocationY();
```

```
//sets the new location 10 px to the right; 10 px down from the current location  
forms.company.elements.faxBtn.setLocation(x+10,y+10);
```

Returns

Number – The x location of the element in pixels.

Sample

```
var x = forms.customer.elements.customer_id.getLocationX();
```

getLocationY

Number getLocationY()

Returns the y location of the current element.

NOTE: getLocationY() can be used with getLocationX() to set the location of an element using the setLocation function. For Example:

```
//returns the X and Y coordinates  
var x = forms.company.elements.faxBtn.getLocationX();  
var y = forms.company.elements.faxBtn.getLocationY();
```

```
//sets the new location 10 px to the right; 10 px down from the current location  
forms.company.elements.faxBtn.setLocation(x+10,y+10);
```

Returns

Number – The y location of the element in pixels.

Sample

```
var y = forms.customer.elements.customer_id.getLocationY();
```

getName

String getName()

Returns the name of an element. (may be null as well)

Returns

String – The name of the element.

Sample

```
var name = forms.customer.elements.customer_id.getName();
```

getScrollX

Number getScrollX()

Returns the x scroll location of the current portal or specified portal - only for a portal where the height of the portal is greater than the height of the portal field(s).

NOTE: getScrollX() can be used with getScrollY() to set the scroll location of a portal using the setScroll function. For Example:

```
//returns the X and Y scroll coordinates  
var x = forms.company.elements.portal50.getScrollX();  
var y = forms.company.elements.portal50.getScrollY();
```

```
//sets the new scroll location  
forms.company.elements.portal50.setScroll(x+10,y+10);
```

Returns

Number – The x scroll location in pixels.

Sample

```
var x = forms.customer.elements.customer_id.getScrollX();
```

getScrollY

Number getScrollY()

Returns the y scroll location of the current portal or specified portal - only for a portal where the height of the portal is greater than the height of the portal field(s).

NOTE: getScrollY() can be used with getScrollX() to set the scroll location of a portal using the setScroll function. For Example:

```
//returns the X and Y scroll coordinates  
var x = forms.company.elements.portal50.getScrollX();  
var y = forms.company.elements.portal50.getScrollY();
```

```
//sets the new scroll location  
forms.company.elements.portal50.setScroll(x+10,y+10);
```

Returns

Number – The y scroll location in pixels.

Sample

```
var y = forms.customer.elements.customer_id.getScrollY();
```

getWidth

Number **getWidth()**

Returns the width of the current element.

NOTE: getWidth() can be used with getHeight() to set the size of an element using the setSize function. For Example:

//returns the width (w) and height (h)

```
var w = forms.company.elements.faxBtn.getWidth();
var h = forms.company.elements.faxBtn.getHeight();
```

//sets the new size

```
forms.company.elements.faxBtn.setSize(w,h);
```

//sets the new size and adds 1 px to both the width and height

```
forms.company.elements.faxBtn.setSize(w+1,h+1);
```

Returns

Number – The width of the element in pixels.

Sample

```
var w = forms.customer.elements.customer_id.getWidth();
```

isEditable

Boolean **isEditable()**

Gets the editable/read-only state of a field; true - editable; false - read-only; ! - the editable/read-only state is inverted (the opposite).

Returns

Boolean – true if editable, false otherwise

Sample

```
var currentState = forms.customer.elements.customer_id.setEditable();
```

putClientProperty

void **putClientProperty(key, value)**

Sets the value for the specified element client property key.

NOTE: Depending on the operating system, a user interface property name may be available.

Parameters

{Object} key – user interface key (depends on operating system)

{Object} value – a predefined value for the key

Returns

void

Sample

```
forms.customer.elements.customer_id.putClientProperty('ToolTipText', 'some text');
```

setLocation

void **setLocation(x, y)**

Sets the location of an element. It takes as input the X (horizontal) and Y (vertical) coordinates - starting from the TOP LEFT side of the screen.

NOTE: getLocationX() can be used with getLocationY() to return the current location of an element; then use the X and Y coordinates with the setLocation function to set a new location. For Example:

//returns the X and Y coordinates

```
var x = forms.company.elements.faxBtn.getLocationX();
```

```
var y = forms.company.elements.faxBtn.getLocationY();
```

//sets the new location 10 px to the right; 10 px down from the current location

```
forms.company.elements.faxBtn.setLocation(x+10,y+10);
```

Parameters

{Number} x – the X coordinate of the element in pixels.

{Number} y – the Y coordinate of the element in pixels.

Returns

void

Sample

```
forms.customer.elements.customer_id.setLocation(200,200);
```

setScroll

```
void setScroll(x, y)
```

Sets the scroll location of a portal. It takes as input the X (horizontal) and Y (vertical) coordinates - starting from the TOP LEFT side of the screen - only for a portal where the height of the portal is greater than the height of the portal field(s).

NOTE: getScrollX() can be used with getScrollY() to return the current scroll location of a portal; then use the X and Y coordinates with the setScroll function to set a new scroll location. For Example:

```
//returns the X and Y coordinates  
var x = forms.company.elements.portal50.getScrollX();  
var y = forms.company.elements.portal50.getScrollY();  
  
//sets the new location  
forms.company.elements.portal50.setScroll(x+10,y+10);
```

Parameters

{Number} x – the X coordinate of the portal scroll location in pixels
{Number} y – the Y coordinate of the portal scroll location in pixels

Returns

void

Sample

```
forms.customer.elements.customer_id.setScroll(200,200);
```

setSize

```
void setSize(width, height)
```

Sets the size of the field. It takes as input the width and the height.

NOTE: getWidth() can be used with getHeight() to set the size of an element using the setSize function. For Example:

```
//returns the width (w) and height (h)  
var w = forms.company.elements.faxBtn.getWidth();  
var h = forms.company.elements.faxBtn.getHeight();  
  
//sets the new size  
forms.company.elements.faxBtn.setSize(w,h);  
  
//sets the new size and adds 1 px to both the width and height  
forms.company.elements.faxBtn.setSize(w+1,h+1);
```

Parameters

{Number} width – the width of the element in pixels.
{Number} height – the height of the element in pixels.

Returns

void

Sample

```
forms.customer.elements.customer_id.setSize(20,30);
```