

JSUnit

Servoy has built-in support for Unit Testing. The integration adds the following to the Servoy environment:

- A JSUnit node to the Solution Explorer, exposing the assert functions used in testcases
- An entry in the content menu of the Active Solution to run the Unit Tests
- A J(S)Unit view for viewing the results of a testrun

Creating testcases is as straightforward as creating a function with a name that starts with 'test_':

```
function test_thisShouldPass() {
    jsunit.assertEquals('This test should pass', true, 5 < 10);
}

function test_thisShouldFail() {
    jsunit.assertEquals('This test should fail', true, 10 < 5);
}
```

The JSUnit node in the Solution Explorer provides easy access to the different supported assert functions

Testcases can be added on application level in the global scope or on form level in the form scope.

Each scope can contain a setUp and/or tearDown function. The setUp function is called BEFORE running each testcase in the scope and the tearDown function is called AFTER running each test in the scope. The setUp and tearDown function allow the developer to create the right circumstances for testcases to run and cleanup afterwards. Note that the setUp() and tearDown() methods are called before and after EACH test methods, as each single test is supposed to be independant.

```
function setUp() {
    //Code here to setup the environment for the testcases in this scope
}
function tearDown() {
    //Code here to cleanup the environment after running the testcases in this scope
}
```

Method Summary

```
void #assertEquals(expected, actual)
Asserts that two values are equal.

void #assertEquals(message, expected, actual)
Asserts that two values are equal.

void #assertFalse(boolean_condition)
Asserts that a condition is false.

void #assertFalse(message, boolean_condition)
Asserts that a condition is false.

void #assertFloatEquals(expectedFloat, actualFloat, tolerance)
Asserts that two floating point values are equal to within a given tolerance.

void #assertFloatEquals(message, expectedFloat, actualFloat, tolerance)
Asserts that two floating point values are equal to within a given tolerance.

void #assertMatches(regularExpression, actualString)
Asserts that a regular expression matches a string.

void #assertMatches(message, regularExpression, actualString)
Asserts that a regular expression matches a string.

void #assertNotNull(object)
Asserts that an object is not null.

void #assertNotNull(message, object)
Asserts that an object is not null.

void #assertNotSame(notExpected, actual)
Asserts that two values are not the same.

void #assertNotSame(message, notExpected, actual)
Asserts that two values are not the same.

void #assertNotUndefined(definedObject)
Asserts that an object is not undefined.

void #assertNotUndefined(message, definedObject)
Asserts that an object is not undefined.

void #assertNull(nullValue)
Asserts that an object is null.

void #assertNull(message, nullValue)
Asserts that an object is null.

void #assertSame(expected, actual)
Asserts that two values are the same.

void #assertSame(message, expected, actual)
Asserts that two values are the same.

void #assertTrue(boolean_condition)
Asserts that a condition is true.

void #assertTrue(message, boolean_condition)
Asserts that a condition is true.

void #assertUndefined(undefinedValue)
Asserts that an object is undefined.

void #assertUndefined(message, undefinedValue)
Asserts that an object is undefined.

void #fail(message)
Fails a test.

void #fail(message, instanceOfCallStack)
Fails a test.

void #fail(message, instanceOfCallStack, userMessage)
Fails a test.
```

Method Details

assertEquals

```
void assertEquals(expected, actual)
```

Asserts that two values are equal. AssertionFailedError is thrown if the actual value does not match the regular expression.

Parameters

{Object} expected – the expected value.

{Object} actual – the actual value.

Returns

void

Sample

```
// Asserts that two values are equal. AssertionFailedError is thrown if the actual value does not match the regular expression.  
jsunit.assertEquals("Solution name test", "someSolution", application.getSolutionName());  
jsunit.assertEquals("Simple math test", 2, 1 + 1);
```

assertEquals

void **assertEquals**(message, expected, actual)

Asserts that two values are equal. AssertionFailedError is thrown if the actual value does not match the regular expression.

Parameters

{String} message – The test description/message.

{Object} expected – the expected value.

{Object} actual – the actual value.

Returns

void

Sample

```
// Asserts that two values are equal. AssertionFailedError is thrown if the actual value does not match the regular expression.  
jsunit.assertEquals("Solution name test", "someSolution", application.getSolutionName());  
jsunit.assertEquals("Simple math test", 2, 1 + 1);
```

assertFalse

void **assertFalse**(boolean_condition)

Asserts that a condition is false. AssertionFailedError is thrown if the evaluation was not false.

Parameters

{Boolean} boolean_condition – the actual value.

Returns

void

Sample

```
// Asserts that a condition is false. AssertionFailedError is thrown if the evaluation was not false.  
jsunit.assertFalse("False test", application.isLastPrintPreviewPrinted());
```

assertFalse

void **assertFalse**(message, boolean_condition)

Asserts that a condition is false. AssertionFailedError is thrown if the evaluation was not false.

Parameters

{String} message – The test description/message.

{Boolean} boolean_condition – the actual value.

Returns

void

Sample

```
// Asserts that a condition is false. AssertionFailedError is thrown if the evaluation was not false.  
jsunit.assertFalse("False test", application.isLastPrintPreviewPrinted());
```

assertFloatEquals

void **assertFloatEquals**(expectedFloat, actualFloat, tolerance)

Asserts that two floating point values are equal to within a given tolerance. AssertionFailedError is thrown if the expected value is not within the tolerance of the actual one.

Parameters

{Number} expectedFloat – the expected value.

{Number} actualFloat – the actual value.

{Number} tolerance – tolerance when comparing.

Returns

void

Sample

```
// Asserts that two floating point values are equal to within a given tolerance. AssertionFailedError is thrown if the expected value is not within the tolerance of the actual one.
jsunit.assertFloatEquals("Float equals test", 3.12, 3.121, 0.0015);
```

assertFloatEquals

void **assertFloatEquals**(message, expectedFloat, actualFloat, tolerance)

Asserts that two floating point values are equal to within a given tolerance. AssertionFailedError is thrown if the expected value is not within the tolerance of the actual one.

Parameters

{String} message – The test description/message.

{Number} expectedFloat – the expected value.

{Number} actualFloat – the actual value.

{Number} tolerance – tolerance when comparing.

Returns

void

Sample

```
// Asserts that two floating point values are equal to within a given tolerance. AssertionFailedError is thrown if the expected value is not within the tolerance of the actual one.
jsunit.assertFloatEquals("Float equals test", 3.12, 3.121, 0.0015);
```

assertMatches

void **assertMatches**(regularExpression, actualString)

Asserts that a regular expression matches a string. AssertionFailedError is thrown if the expected value is not the actual one.

Parameters

{Object} regularExpression – the regular expression used for matching.

{String} actualString – the actual value to be matched.

Returns

void

Sample

```
// Asserts that a regular expression matches a string. AssertionFailedError is thrown if the expected value is not the actual one.
jsunit.assertMatches(new RegExp("gr(a|e)y"), "gray");
```

assertMatches

void **assertMatches**(message, regularExpression, actualString)

Asserts that a regular expression matches a string. AssertionFailedError is thrown if the expected value is not the actual one.

Parameters

{String} message – The test description/message.

{Object} regularExpression – the regular expression used for matching.

{String} actualString – the actual value to be matched.

Returns

void

Sample

```
// Asserts that a regular expression matches a string. AssertionFailedError is thrown if the expected value is not the actual one.
jsunit.assertMatches("Match test", new RegExp("gr(a|e)y"), "gray");
```

assertNotNull

void **assertNotNull**(object)

Asserts that an object is not null. AssertionFailedError is thrown if the object is not null.

Parameters

{Object} object – the actual value.

Returns

void

Sample

```
// Asserts that an object is not null. AssertionFailedError is thrown if the object is not null.  
var a; // this is undefined, not null  
jsunit.assertNotNull(a);
```

assertNotNull

void **assertNotNull**(message, object)

Asserts that an object is not null. AssertionFailedError is thrown if the object is not null.

Parameters

{String} message – The test description/message.

{Object} object – the actual value.

Returns

void

Sample

```
// Asserts that an object is not null. AssertionFailedError is thrown if the object is not null.  
var a; // this is undefined, not null  
jsunit.assertNotNull("Not null test", a);
```

assertNotSame

void **assertNotSame**(notExpected, actual)

Asserts that two values are not the same. AssertionFailedError is thrown if the expected value is the actual one.

Parameters

{Object} notExpected – the value that is not expected.

{Object} actual – the actual value.

Returns

void

Sample

```
// Asserts that two values are not the same. AssertionFailedError is thrown if the expected value is the actual one.  
var a = new Date(1990, 1, 1);  
var b = new Date(1990, 1, 1);  
jsunit.assertNotSame(a, b);  
jsunit.assertEquals("But equals", a, b);
```

assertNotSame

void **assertNotSame**(message, notExpected, actual)

Asserts that two values are not the same. AssertionFailedError is thrown if the expected value is the actual one.

Parameters

{String} message – The test description/message.

{Object} notExpected – the value that is not expected.

{Object} actual – the actual value.

Returns

void

Sample

```
// Asserts that two values are not the same. AssertionFailedError is thrown if the expected value is the actual one.  
var a = new Date(1990, 1, 1);  
var b = new Date(1990, 1, 1);  
jsunit.assertNotSame("Not same test", a, b);  
jsunit.assertEquals("But equals", a, b);
```

assertNotUndefined

void **assertNotUndefined**(definedObject)

Asserts that an object is not undefined. AssertionFailedError is thrown if the object is undefined.

Parameters

{Object} definedObject – the actual value.

Returns

void

Sample

```
// Asserts that an object is not undefined. AssertionFailedError is thrown if the object is undefined.  
var a = 0;  
jsunit.assertNotUndefined(a);
```

assertNotUndefined

void **assertNotUndefined**(message, definedObject)

Asserts that an object is not undefined. AssertionFailedError is thrown if the object is undefined.

Parameters

{String} message – The test description/message.

{Object} definedObject – the actual value.

Returns

void

Sample

```
// Asserts that an object is not undefined. AssertionFailedError is thrown if the object is undefined.  
var a = 0;  
jsunit.assertNotUndefined("Not undefined test", a);
```

assertNull

void **assertNull**(nullValue)

Asserts that an object is null. AssertionFailedError is thrown if the object is not null.

Parameters

{Object} nullValue – the actual value.

Returns

void

Sample

```
// Asserts that an object is null. AssertionFailedError is thrown if the object is not null.  
jsunit.assertNull("Null test", null);
```

assertNull

void **assertNull**(message, nullValue)

Asserts that an object is null. AssertionFailedError is thrown if the object is not null.

Parameters

{String} message – The test description/message.

{Object} nullValue – the actual value.

Returns

void

Sample

```
// Asserts that an object is null. AssertionFailedError is thrown if the object is not null.  
jsunit.assertNull("Null test", null);
```

assertSame

void **assertSame**(expected, actual)

Asserts that two values are the same. AssertionFailedError is thrown if the expected value is not the actual one.

Parameters

{Object} expected – the expected value.

{Object} actual – the actual value.

Returns

void

Sample

```
// Asserts that two values are the same. AssertionFailedError is thrown if the expected value is not the actual one.  
var a = new Date(1990, 1, 1);  
var b = a;  
jsunit.assertSame(a, b);
```

assertSame

```
void assertSame(message, expected, actual)
```

Asserts that two values are the same. AssertionFailedError is thrown if the expected value is not the actual one.

Parameters

{[String](#)} message – The test description/message.

{[Object](#)} expected – the expected value.

{[Object](#)} actual – the actual value.

Returns

void

Sample

```
// Asserts that two values are the same. AssertionFailedError is thrown if the expected value is not the actual  
one.  
var a = new Date(1990, 1, 1);  
var b = a;  
junit.assertSame("Same test", a, b);
```

[assertTrue](#)

```
void assertTrue(boolean_condition)
```

Asserts that a condition is true. AssertionFailedError is thrown if the evaluation was not true.

Parameters

{[Boolean](#)} boolean_condition – the actual value.

Returns

void

Sample

```
// Asserts that a condition is true. AssertionFailedError is thrown if the evaluation was not true.  
junit.assertTrue("True test", application.isLastPrintPreviewPrinted());
```

[assertFalse](#)

```
void assertFalse(message, boolean_condition)
```

Asserts that a condition is false. AssertionFailedError is thrown if the evaluation was not false.

Parameters

{[String](#)} message – The test description/message.

{[Boolean](#)} boolean_condition – the actual value.

Returns

void

Sample

```
// Asserts that a condition is false. AssertionFailedError is thrown if the evaluation was not false.  
junit.assertFalse("False test", application.isLastPrintPreviewPrinted());
```

[assertUndefined](#)

```
void assertUndefined(undefinedValue)
```

Asserts that an object is undefined. AssertionFailedError is thrown if the object is defined.

Parameters

{[Object](#)} undefinedValue – the actual value.

Returns

void

Sample

```
// Asserts that an object is undefined. AssertionFailedError is thrown if the object is defined.  
junit.assertUndefined("Undefined test", thisIsUndefined);
```

[assertFalse](#)

```
void assertFalse(message, undefinedValue)
```

Asserts that an object is undefined. AssertionFailedError is thrown if the object is defined.

Parameters

{[String](#)} message – The test description/message.

{[Object](#)} undefinedValue – the actual value.

Returns

void

Sample

```
// Asserts that an object is undefined. AssertionFailedError is thrown if the object is defined.  
jsunit.assertUndefined(thisIsUndefined);
```

fail

void **fail**(message)

Fails a test. AssertionFailedError is always thrown.

Parameters

{String} message – The test description/message. This is usually the only parameter specified when calling this method.

Returns

void

Sample

```
// Fails a test. AssertionFailedError is always thrown.  
jsunit.fail("Fail test");  
jsunit.fail("test", null, "Fail"); // 2nd param is not used in Servoy, params 3 and 1 get merged to form a  
message. The result is the same as in the line above.
```

fail

void **fail**(message, instanceOfCallStack)

Fails a test. AssertionFailedError is always thrown.

Parameters

{String} message – The test description/message. This is usually the only parameter specified when calling this method.

{Object} instanceOfCallStack – an internal JSUnit call stack. Use null for this if you want to get to the next optional parameter. Usually not specified.

Returns

void

Sample

```
// Fails a test. AssertionFailedError is always thrown.  
jsunit.fail("Fail test");  
jsunit.fail("test", null, "Fail"); // 2nd param is not used in Servoy, params 3 and 1 get merged to form a  
message. The result is the same as in the line above.
```

fail

void **fail**(message, instanceOfCallStack, userMessage)

Fails a test. AssertionFailedError is always thrown.

Parameters

{String} message – The test description/message. This is usually the only parameter specified when calling this method.

{Object} instanceOfCallStack – an internal JSUnit call stack. Use null for this if you want to get to the next optional parameter. Usually not specified.

{String} userMessage – a user message. Usually not specified.

Returns

void

Sample

```
// Fails a test. AssertionFailedError is always thrown.  
jsunit.fail("Fail test");  
jsunit.fail("test", null, "Fail"); // 2nd param is not used in Servoy, params 3 and 1 get merged to form a  
message. The result is the same as in the line above.
```