# **JSPart**



Apr 07, 2024 13:17

# **Supported Clients**

SmartClient WebClient NGClient

# **Constants Summary**

Number BODY Constant use for specifying the type of form parts. Number **FOOTER** Constant use for specifying the type of form parts. Number **HEADER** Constant use for specifying the type of form parts. LEADING\_GRAND\_SUMMARY Constant use for specifying the type of form parts. Number LEADING\_SUBSUMMARY Constant use for specifying the type of form parts. Number Number TITLE\_FOOTER Constant use for specifying the type of form parts. TITLE\_HEADER Constant use for specifying the type of form parts. Number Number TRAILING\_GRAND\_SUMMARY Constant use for specifying the type of form parts. Number TRAILING\_SUBSUMMARY Constant use for specifying the type of form parts.

# **Property Summary**

Boolean	allowBreakAcrossPageBounds	When set, the remainder of a selected part that does not fit on the page currently being printed, will not be transported to the next page - it will break where the page ends and continue on the next page.
String	background	The background color of the form part.
Boolean	discardRemainderAfterBreak	When set, the remainder of a selected part that is broken due to the page ending will not be printed on the next page - it will be discarded.
String	groupbyDataProviderIDs	For Leading Subsummary or Trailing Subsummary parts, one or more dataproviders can be added as Break (GroupBy) dataproviders.
Number	height	The height of a selected part; specified in pixels.
Number	pageBreakAfterOccurrence	A page break will be inserted after a specified number of occurences of a selected part.
Boolean	pageBreakBefore	When set, a page break will be inserted before each occurrence of a selected part.
Boolean	restartPageNumber	When set, page numbering will be restarted after each occurrence of a selected part.
Boolean	sinkWhenLast	When set, the last part on a page (such as a Trailing Grand Summary part) will "sink" to the lowest part of the page when there is free space.
String	styleClass	The Cascading Style Sheet (CSS) class name applied to the part.

# **Methods Summary**

String	getComment()	Returns the comment of this component.
Number	getPartType()	The type of this part.
Number	getPartYOffset()	The Y offset of the part on the form, this will include all the super forms parts if this form extends a form.
UUID	getUUID()	Returns the UUID of this component.

# **Constants Details**

# BODY

Constant use for specifying the type of form parts.

This is the default part that is repeated for each record (being displayed and/or printed).

# Returns

Number

### **Supported Clients**

SmartClient, WebClient, NGClient

### Sample

```
var body = form.newPart(JSPart.BODY, 320);
```

# **FOOTER**

Constant use for specifying the type of form parts.

A footer is displayed at the bottom of each page when printed ad can contain summaries of the current selection of records. In List view, the footer is displayed at the bottom of the list of records.

#### Returns

Number

### Supported Clients

SmartClient, WebClient, NGClient

#### Sample

```
var footer = form.newPart(JSPart.FOOTER, 440);
```

#### **HEADER**

Constant use for specifying the type of form parts.

A header is displayed at the top of each page when printed and can contain summaries of the current selection of records. In List view the header is displayed above the list of records. In tableview the default column headers will not be there if this is specified.

#### Returns

Number

### **Supported Clients**

SmartClient,WebClient,NGClient

#### Sample

```
var header = form.newPart(JSPart.HEADER, 80);
```

### LEADING\_GRAND\_SUMMARY

Constant use for specifying the type of form parts.

A Leading Grand Summary can be placed before the body part. It can contain summary fields that will generate summaries for the entire foundset. In tableview the default column headers will not be there if this is specified.

### Returns

Number

### Supported Clients

SmartClient, WebClient

### Sample

```
var leadingGrandSummary = form.newPart(JSPart.LEADING_GRAND_SUMMARY, 120);
```

# LEADING\_SUBSUMMARY

Constant use for specifying the type of form parts.

A Leading Subsummary can be placed before the body part. There can be multiple Leading Subsummaries per form. Each Subsummary part has a set of Group By fields which are used to group data together. Each Subsummary part can contain summary fields, which will be printed once for each group of data. This part is only shown in printing

### Returns

Number

### Supported Clients

SmartClient,WebClient

### Sample

```
var leadingSubsummary = form.newPart(JSPart.LEADING_SUBSUMMARY, 160);
```

### TITLE\_FOOTER

Constant use for specifying the type of form parts.

Appears only once on the first page of a printed report. If a Footer is available, it is replaced by the Title Footer on the first page.

#### Returns

Number

#### Supported Clients

SmartClient,WebClient

#### Sample

```
var titleFooter = form.newPart(JSPart.TITLE_FOOTER, 500);
```

### TITLE\_HEADER

Constant use for specifying the type of form parts.

Appears only once on the first page of a printed report or on top of the first screen of a foundset. If a Header is available it is replace by the Title Header on the first page.

This part is also shown in a normal none printing form, because it can be used to place components in a tableview form and keep the default table header columns. Other parts as the HEADER will remove the default header columns.

#### Returns

Number

#### Supported Clients

SmartClient, WebClient, NGClient

#### Sample

```
var titleHeader = form.newPart(JSPart.TITLE_HEADER, 40);
```

### TRAILING\_GRAND\_SUMMARY

Constant use for specifying the type of form parts.

A Trailing Grand Summary can be placed after the body part. It can contain summary fields that will generate summaries for the entire foundset.

### Returns

Number

### Supported Clients

SmartClient, WebClient

### Sample

```
var trailingGrandSummary = form.newPart(JSPart.TRAILING_GRAND_SUMMARY, 400);
```

# TRAILING\_SUBSUMMARY

Constant use for specifying the type of form parts.

A Trailing Subsummary can be placed after the body part. There can be multiple Trailing Subsummaries per form. Each Subsummary part has a set of Group By fields which are used to group data together. Each Subsummary part can contain summary fields, which will be printed once for each group of data. This part is only shown in printing

### Returns

Number

### Supported Clients

SmartClient, WebClient

### Sample

```
var trailingSubsummary = form.newPart(JSPart.TRAILING_SUBSUMMARY, 360);
```

# **Property Details**

### allowBreakAcrossPageBounds

When set, the remainder of a selected part that does not fit on the page currently being printed, will not be transported to the next page - it will break where the page ends and continue on the next page.

NOTE: Make sure to set this option when you are printing more than one page per record.

#### Returns

**Boolean** 

#### Supported Clients

SmartClient, WebClient

#### Sample

```
var body = form.newPart(JSPart.BODY, 320);
body.allowBreakAcrossPageBounds = true;
body.discardRemainderAfterBreak = true;
```

### background

The background color of the form part.

NOTE: When no background color has been set, the default background color will be determined by the Look and Feel (LAF) that has been selected in Application Preferences.

#### Returns

String

### **Supported Clients**

SmartClient, WebClient, NGClient

### Sample

```
var body = form.newPart(JSPart.BODY, 320);
body.background = 'green';
```

### discardRemainderAfterBreak

When set, the remainder of a selected part that is broken due to the page ending will not be printed on the next page - it will be discarded.

### Returns

Boolean

### **Supported Clients**

SmartClient,WebClient

### Sample

```
var body = form.newPart(JSPart.BODY, 320);
body.allowBreakAcrossPageBounds = true;
body.discardRemainderAfterBreak = true;
```

# groupbyDataProviderIDs

For Leading Subsummary or Trailing Subsummary parts, one or more dataproviders can be added as Break (GroupBy) dataproviders. The Leading/Trailing Subsummary parts will be displayed once for each resulted group of data.

# Returns

String

### Supported Clients

SmartClient, WebClient, NGClient

### Sample

```
var leadingSubsummary = form.newPart(JSPart.LEADING_SUBSUMMARY, 160);
leadingSubsummary.groupbyDataProviderIDs = 'my_table_text';
```

### height

The height of a selected part; specified in pixels.

This height property is the lowerbound as its ending Y value (0 == top of the form).

#### Returns

Number

### **Supported Clients**

SmartClient, WebClient, NGClient

#### Sample

```
var part = form.newPart(JSPart.HEADER, 100);
part.height = 200;
```

### pageBreakAfterOccurrence

A page break will be inserted after a specified number of occurences of a selected part.

#### Returns

Number

### **Supported Clients**

SmartClient, WebClient

#### Sample

```
var body = form.newPart(JSPart.BODY, 320);
body.pageBreakAfterOccurrence = 2;
```

#### pageBreakBefore

When set, a page break will be inserted before each occurrence of a selected part.

### Returns

Boolean

### **Supported Clients**

SmartClient,WebClient

### Sample

```
var leadingSubsummary = form.newPart(JSPart.LEADING_SUBSUMMARY, 160);
leadingSubsummary.groupbyDataProviderIDs = 'my_table_text';
leadingSubsummary.pageBreakBefore = true;
```

### restartPageNumber

When set, page numbering will be restarted after each occurrence of a selected part.

### Returns

Boolean

### Supported Clients

SmartClient, WebClient

### Sample

```
var trailingSubsummary = form.newPart(JSPart.TRAILING_SUBSUMMARY, 360);
trailingSubsummary.groupbyDataProviderIDs = 'my_table_text';
trailingSubsummary.restartPageNumber = true;
```

### sinkWhenLast

When set, the last part on a page (such as a Trailing Grand Summary part) will "sink" to the lowest part of the page when there is free space.

# Returns

Boolean

### Supported Clients

SmartClient,WebClient

#### Sample

```
var trailingGrandSummary = form.newPart(JSPart.TRAILING_GRAND_SUMMARY, 400);
trailingGrandSummary.sinkWhenLast = true;
```

### styleClass

The Cascading Style Sheet (CSS) class name applied to the part.

#### Returns

String

### **Supported Clients**

SmartClient,WebClient,NGClient

#### Sample

```
var body = form.newPart(JSPart.BODY, 320);
body.styleClass = 'myBody';
```

# **Methods Details**

# getComment()

Returns the comment of this component.

#### Returns

String

### **Supported Clients**

SmartClient, WebClient, NGClient

#### Sample

```
var comment = solutionModel.getForm("my_form").getButton("my_button").getComment();
application.output(comment);
```

### getPartType()

The type of this part.

### Returns

Number A number representing the type of the form part.

# **Supported Clients**

SmartClient,WebClient,NGClient

### Sample

# getPartYOffset()

The Y offset of the part on the form, this will include all the super forms parts if this form extends a form.

### Returns

Number A number holding the Y offset of the form part.

# **Supported Clients**

SmartClient, WebClient, NGClient

### Sample

# getUUID()

Returns the UUID of this component.

### Returns

UUID

# **Supported Clients**

SmartClient, WebClient, NGClient

### Sample

```
var button_uuid = solutionModel.getForm("my_form").getButton("my_button").getUUID();
application.output(button_uuid.toString());
```