SCROLLBAR

Feb 21, 2024 21:04

Supported Clients

SmartClient WebClient NGClient

Constants Summary

Number	HORIZONTAL_SCROLLBAR_ALWAYS	Used to set the horizontal scroll bar policy so that horizontal scrollbars are always displayed.
Number	HORIZONTAL_SCROLLBAR_AS_NEEDED	Used to set the horizontal scroll bar policy so that horizontal scrollbars are displayed only when needed.
Number	HORIZONTAL_SCROLLBAR_NEVER	Used to set the horizontal scroll bar policy so that horizontal scrollbars are never displayed.
Number	SCROLLBARS_WHEN_NEEDED	Used to set the horizontal and vertical scroll bar policy so that both scrollbars are displayed only when needed.
Number	VERTICAL_SCROLLBAR_ALWAYS	Used to set the vertical scroll bar policy so that vertical scrollbars are always displayed.
Number	VERTICAL_SCROLLBAR_AS_NEEDED	Used to set the vertical scroll bar policy so that vertical scrollbars are displayed only when needed.
Number	VERTICAL_SCROLLBAR_NEVER	Used to set the vertical scroll bar policy so that vertical scrollbars are never displayed.

Constants Details

HORIZONTAL_SCROLLBAR_ALWAYS

Used to set the horizontal scroll bar policy so that horizontal scrollbars are always displayed.

Returns

Number

Supported Clients

SmartClient,WebClient,NGClient

Sample

```
var alwaysScrollbars = form.newField('my_table_text', JSField.TEXT_AREA, 230, 10, 100, 100);
alwaysScrollbars.scrollbars = SM_SCROLLBAR.HORIZONTAL_SCROLLBAR_ALWAYS | SM_SCROLLBAR.VERTICAL_SCROLLBAR_ALWAYS;
```

HORIZONTAL_SCROLLBAR_AS_NEEDED

Used to set the horizontal scroll bar policy so that horizontal scrollbars are displayed only when needed.

Returns

Number

Supported Clients

SmartClient,WebClient,NGClient

Sample

```
var neededScrollbars = form.newField('my_table_text', JSField.TEXT_AREA, 120, 10, 100, 100);
neededScrollbars.scrollbars = SM_SCROLLBAR.HORIZONTAL_SCROLLBAR_AS_NEEDED | SM_SCROLLBAR.
VERTICAL_SCROLLBAR_AS_NEEDED;
```

HORIZONTAL_SCROLLBAR_NEVER

Used to set the horizontal scroll bar policy so that horizontal scrollbars are never displayed.

Returns

Number

Supported Clients

SmartClient,WebClient,NGClient

Sample

```
var noScrollbars = form.newField('my_table_text', JSField.TEXT_AREA, 10, 10, 100, 100);
noScrollbars.scrollbars = SM_SCROLLBAR.HORIZONTAL_SCROLLBAR_NEVER | SM_SCROLLBAR.VERTICAL_SCROLLBAR_NEVER;
```

SCROLLBARS_WHEN_NEEDED

Used to set the horizontal and vertical scroll bar policy so that both scrollbars are displayed only when needed.

Returns

Number

Supported Clients

SmartClient,WebClient,NGClient

Sample

```
var neededScrollbars = form.newField('my_table_text', JSField.TEXT_AREA, 120, 10, 100, 100);
// This is the default option, but if you really want you can set it explicitly.
neededScrollbars.scrollbars = SM_SCROLLBAR.SCROLLBARS_WHEN_NEEDED;
```

VERTICAL_SCROLLBAR_ALWAYS

Used to set the vertical scroll bar policy so that vertical scrollbars are always displayed.

Returns

Number

Supported Clients

SmartClient,WebClient,NGClient

Sample

```
var alwaysScrollbars = form.newField('my_table_text', JSField.TEXT_AREA, 230, 10, 100, 100);
alwaysScrollbars.scrollbars = SM_SCROLLBAR.HORIZONTAL_SCROLLBAR_ALWAYS | SM_SCROLLBAR.VERTICAL_SCROLLBAR_ALWAYS;
```

VERTICAL_SCROLLBAR_AS_NEEDED

Used to set the vertical scroll bar policy so that vertical scrollbars are displayed only when needed.

Returns

Number

Supported Clients

SmartClient,WebClient,NGClient

Sample

```
var neededScrollbars = form.newField('my_table_text', JSField.TEXT_AREA, 120, 10, 100, 100);
neededScrollbars.scrollbars = SM_SCROLLBAR.HORIZONTAL_SCROLLBAR_AS_NEEDED | SM_SCROLLBAR.
VERTICAL_SCROLLBAR_AS_NEEDED;
```

VERTICAL_SCROLLBAR_NEVER

Used to set the vertical scroll bar policy so that vertical scrollbars are never displayed.

Returns

Number

Supported Clients

SmartClient,WebClient,NGClient

Sample

```
var noScrollbars = form.newField('my_table_text', JSField.TEXT_AREA, 10, 10, 100, 100);
noScrollbars.scrollbars = SM_SCROLLBAR.HORIZONTAL_SCROLLBAR_NEVER | SM_SCROLLBAR.VERTICAL_SCROLLBAR_NEVER;
```