

# ColumnInfo

 Apr 06, 2024 15:09

Supported Clients

SmartClient WebClient NGClient MobileClient

| Property Summary |                                      |                                                                                                                              |
|------------------|--------------------------------------|------------------------------------------------------------------------------------------------------------------------------|
| Number           | <a href="#">autoEnterSubType</a>     | The subtype of autoenter configured for the column.                                                                          |
| Number           | <a href="#">autoEnterType</a>        | The type of autoenter configured for the column.                                                                             |
| String           | <a href="#">converterName</a>        | The name of the converter used for this column.                                                                              |
| String           | <a href="#">converterProperties</a>  | The properties of the converter used for this column.                                                                        |
| String           | <a href="#">databaseDefaultValue</a> | The database default value that is used when autoenter is set to database default.                                           |
| String           | <a href="#">databaseSequenceName</a> | The database sequence name that is used when autoenter is set to sequence and autoenter subtype is set to database sequence. |
| String           | <a href="#">defaultFormat</a>        | The default format of the column.                                                                                            |
| String           | <a href="#">defaultValue</a>         | The value that is used when autoenter is set to custom value.                                                                |
| String           | <a href="#">description</a>          | The description of the column.                                                                                               |
| String           | <a href="#">foreignType</a>          | The foreign type of the column.                                                                                              |
| String           | <a href="#">lookupValue</a>          | The lookup value that is used when autotype is set to lookup.                                                                |
| String           | <a href="#">titleText</a>            | The title of the column.                                                                                                     |
| String           | <a href="#">validatorName</a>        | The name of the validator used for the column.                                                                               |
| String           | <a href="#">validatorProperties</a>  | The properties of the validator used for the column.                                                                         |

Property Details

autoEnterSubType

The subtype of autoenter configured for the column. The available options depend on the type of autoenter.  
  
If autoenter is set to system value, then the subtype can be one of: none, creation datetime, creation username, modification datetime, modification username, database managed, creation user uid, modification user uid, creation server datetime or modification server datetime.  
  
If autoenter is set to sequence, then the subtype can be one of: none, Servoy sequence, database sequence, database identity or universally unique identifier.

Returns

[Number](#)

Supported Clients

SmartClient,WebClient,NGClient,MobileClient

Sample

autoEnterType

The type of autoenter configured for the column. Can be one of: none, system value, sequence, custom value or lookup value.

Returns

[Number](#)

Supported Clients

SmartClient,WebClient,NGClient,MobileClient

Sample

converterName

The name of the converter used for this column.

Returns

[String](#)

Supported Clients

SmartClient,WebClient,NGClient,MobileClient

---

**Sample****converterProperties**

The properties of the converter used for this column.

**Returns**

[String](#)

**Supported Clients**

SmartClient,WebClient,NGClient,MobileClient

**Sample****databaseDefaultValue**

The database default value that is used when autoenter is set to database default.

**Returns**

[String](#)

**Supported Clients**

SmartClient,WebClient,NGClient,MobileClient

**Sample****databaseSequenceName**

The database sequence name that is used when autoenter is set to sequence and autoenter subtype is set to database sequence.

**Returns**

[String](#)

**Supported Clients**

SmartClient,WebClient,NGClient,MobileClient

**Sample****defaultFormat**

The default format of the column.  
Currently only strings or numbers are supported.

**Returns**

[String](#)

**Supported Clients**

SmartClient,WebClient,NGClient,MobileClient

**Sample****defaultValue**

The value that is used when autoenter is set to custom value.

**Returns**

[String](#)

**Supported Clients**

SmartClient,WebClient,NGClient,MobileClient

**Sample****description**

The description of the column.

**Returns**

[String](#)

---

**Supported Clients**

SmartClient,WebClient,NGClient,MobileClient

**Sample****foreignType**

The foreign type of the column. It is used for foreign key columns, to hold the foreign table they point to.

**Returns**

[String](#)

**Supported Clients**

SmartClient,WebClient,NGClient,MobileClient

**Sample****lookupValue**

The lookup value that is used when autotype is set to lookup.

**Returns**

[String](#)

**Supported Clients**

SmartClient,WebClient,NGClient,MobileClient

**Sample****titleText**

The title of the column.

**Returns**

[String](#)

**Supported Clients**

SmartClient,WebClient,NGClient,MobileClient

**Sample****validatorName**

The name of the validator used for the column.

**Returns**

[String](#)

**Supported Clients**

SmartClient,WebClient,NGClient,MobileClient

**Sample****validatorProperties**

The properties of the validator used for the column.

**Returns**

[String](#)

**Supported Clients**

SmartClient,WebClient,NGClient,MobileClient

**Sample**