


Part

 Apr 05, 2024 18:14

Supported Clients

SmartClient WebClient NGClient

Property Summary		
Boolean	allowBreakAcrossPageBounds	When set, the remainder of a selected part that does not fit on the page currently being printed, will not be transported to the next page - it will break where the page ends and continue on the next page.
String	background	The background color of the form part.
Boolean	discardRemainderAfterBreak	When set, the remainder of a selected part that is broken due to the page ending will not be printed on the next page - it will be discarded.
String	groupbyDataProviderIDs	For Leading Subsummary or Trailing Subsummary parts, one or more dataproviders can be added as Break (GroupBy) dataproviders.
Number	height	The height of a selected part; specified in pixels.
Number	pageBreakAfterOccurrence	A page break will be inserted after a specified number of occurrences of a selected part.
Boolean	pageBreakBefore	When set, a page break will be inserted before each occurrence of a selected part.
Number	partType	The type of this part.
Boolean	restartPageNumber	When set, page numbering will be restarted after each occurrence of a selected part.
Boolean	sinkWhenLast	When set, the last part on a page (such as a Trailing Grand Summary part) will "sink" to the lowest part of the page when there is free space.
String	styleClass	The Cascading Style Sheet (CSS) class name applied to the part.

Property Details

allowBreakAcrossPageBounds

When set, the remainder of a selected part that does not fit on the page currently being printed, will not be transported to the next page - it will break where the page ends and continue on the next page.

NOTE: Make sure to set this option when you are printing more than one page per record.

Returns

[Boolean](#)

Supported Clients

SmartClient,WebClient

Sample

background

The background color of the form part.

NOTE: When no background color has been set, the default background color will be determined by the Look and Feel (LAF) that has been selected in Application Preferences.

Returns

[String](#)

Supported Clients

SmartClient,WebClient,NGClient

Sample

discardRemainderAfterBreak

When set, the remainder of a selected part that is broken due to the page ending will not be printed on the next page - it will be discarded.

Returns

[Boolean](#)

Supported Clients

SmartClient,WebClient

Sample**groupByDataProviderIDs**

For Leading Subsummary or Trailing Subsummary parts, one or more dataproviders can be added as Break (GroupBy) dataproviders. The Leading/Trailing Subsummary parts will be displayed once for each resulted group of data.

Returns

[String](#)

Supported Clients

SmartClient,WebClient,NGClient

Sample**height**

The height of a selected part; specified in pixels.

This height property is the lowerbound as its ending Y value (0 == top of the form).

Returns

[Number](#)

Supported Clients

SmartClient,WebClient,NGClient

Sample**pageBreakAfterOccurrence**

A page break will be inserted after a specified number of occurrences of a selected part.

Returns

[Number](#)

Supported Clients

SmartClient,WebClient

Sample**pageBreakBefore**

When set, a page break will be inserted before each occurrence of a selected part.

Returns

[Boolean](#)

Supported Clients

SmartClient,WebClient

Sample**partType**

The type of this part.

Returns

[Number](#)

Supported Clients


SmartClient,WebClient,NGClient

Sample**restartPageNumber**

When set, page numbering will be restarted after each occurrence of a selected part.

Returns[Boolean](#)**Supported Clients**

SmartClient,WebClient

Sample**sinkWhenLast**

When set, the last part on a page (such as a Trailing Grand Summary part) will "sink" to the lowest part of the page when there is free space.

Returns[Boolean](#)**Supported Clients**

SmartClient,WebClient

Sample**styleClass**

The Cascading Style Sheet (CSS) class name applied to the part.

Returns[String](#)**Supported Clients**

SmartClient,WebClient,NGClient

Sample