Part



String

Boolean

Number

Boolean Boolean

String

Apr 05, 2024 18:14

Supported Clients

SmartClient WebClient NGClient

Property Summary

allowBreakAcrossPageBounds When set, the remainder of a selected part that does not fit on the page currently being **Boolean**

printed, will not be transported to the next page - it will break where the page ends and

continue on the next page.

The background color of the form part. background

Boolean discardRemainderAfterBreak When set, the remainder of a selected part that is broken due to the page ending will not

be printed on the next page - it will be discarded.

For Leading Subsummary or Trailing Subsummary parts, one or more dataproviders can String groupbyDataProviderIDs

be added as Break (GroupBy) dataproviders.

height The height of a selected part; specified in pixels. Number

Number pageBreakAfterOccurrence A page break will be inserted after a specified number of occurences of a selected part.

When set, a page break will be inserted before each occurrence of a selected part.

The type of this part.

restartPageNumber When set, page numbering will be restarted after each occurrence of a selected part. sinkWhenLast

When set, the last part on a page (such as a Trailing Grand Summary part) will "sink" to

the lowest part of the page when there is free space.

The Cascading Style Sheet (CSS) class name applied to the part.

Property Details

allowBreakAcrossPageBounds

pageBreakBefore

partType

styleClass

When set, the remainder of a selected part that does not fit on the page currently being printed, will not be transported to the next page - it will break where the page ends and continue on the next page.

NOTE: Make sure to set this option when you are printing more than one page per record.

Returns

Boolean

Supported Clients

SmartClient, WebClient

Sample

background

The background color of the form part.

NOTE: When no background color has been set, the default background color will be determined by the Look and Feel (LAF) that has been selected in Application Preferences.

Returns

String

Supported Clients

SmartClient, WebClient, NGClient

Sample

discardRemainderAfterBreak

When set, the remainder of a selected part that is broken due to the page ending will not be printed on the next page - it will be discarded.

Returns

Boolean

Supported Clients

SmartClient, WebClient

Sample

groupbyDataProviderIDs

For Leading Subsummary or Trailing Subsummary parts, one or more dataproviders can be added as Break (GroupBy) dataproviders. The Leading/Trailing Subsummary parts will be displayed once for each resulted group of data.

Returns

String

Supported Clients

SmartClient, WebClient, NGClient

Sample

height

The height of a selected part; specified in pixels.

This height property is the lowerbound as its ending Y value (0 == top of the form).

Returns

Number

Supported Clients

SmartClient, WebClient, NGClient

Sample

pageBreakAfterOccurrence

A page break will be inserted after a specified number of occurences of a selected part.

Returns

Number

Supported Clients

SmartClient,WebClient

Sample

pageBreakBefore

When set, a page break will be inserted before each occurrence of a selected part.

Returns

Boolean

Supported Clients

SmartClient,WebClient

Sample

partType

The type of this part.

Returns

Number

Supported Clients

SmartClient, WebClient, NGClient

Sample

restartPageNumber

When set, page numbering will be restarted after each occurrence of a selected part.

Returns

Boolean

Supported Clients

SmartClient,WebClient

Sample

sinkWhenLast

When set, the last part on a page (such as a Trailing Grand Summary part) will " \sinh " to the lowest part of the page when there is free space.

Returns

Boolean

Supported Clients

SmartClient,WebClient

Sample

styleClass

The Cascading Style Sheet (CSS) class name applied to the part.

Returns

String

Supported Clients

SmartClient,WebClient,NGClient

Sample