

ALIGNMENT

 Apr 12, 2024 07:36

Supported Clients

SmartClient WebClient NGClient

Constants Summary		
Number	BOTTOM	Constant used for setting vertical alignment for components.
Number	CENTER	Constant used for setting horizontal and vertical alignment for components.
Number	DEFAULT	Constant used for setting horizontal and vertical alignment.
Number	LEFT	Constant used for setting horizontal alignment for components.
Number	RIGHT	Constant used for setting horizontal alignment for components.
Number	TOP	Constant used for setting vertical alignment for components.

Constants Details

BOTTOM
Constant used for setting vertical alignment for components.
It makes the text inside the component be bottom aligned vertically.

Returns

Number

Supported Clients
SmartClient,WebClient,NGClient
Sample

```
var bottomAlignedLabel = form.newLabel('BOTTOM', 520, 10, 50, 300);
bottomAlignedLabel.verticalAlignment = SM_ALIGNMENT.BOTTOM;
```

CENTER
Constant used for setting horizontal and vertical alignment for components. If used for horizontal alignment, then the text of the component will be horizontally centered. Similarly, if used for vertical alignment, then the text of the component will be vertically centered.

Returns

Number

Supported Clients
SmartClient,WebClient,NGClient
Sample

```
var hCenteredLabel = form.newLabel('CENTER', 10, 40, 300, 20);
hCenteredLabel.horizontalAlignment = SM_ALIGNMENT.CENTER;
var vCenterAlignedLabel = form.newLabel('CENTER', 460, 10, 50, 300);
vCenterAlignedLabel.verticalAlignment = SM_ALIGNMENT.CENTER
```

DEFAULT
Constant used for setting horizontal and vertical alignment. DEFAULT value makes the alignment behave as if it was not changed before.

Returns

Number

Supported Clients
SmartClient,WebClient,NGClient

Sample

```
var hLabel = myJSForm.getLabel('label_name');  
if (hLabel.horizontalAlignment == SM_ALIGNMENT.LEFT) hLabel.horizontalAlignment = SM_ALIGNMENT.DEFAULT;
```

LEFT

Constant used for setting horizontal alignment for components.
It makes the text inside the component be left aligned horizontally.

Returns

[Number](#)

Supported Clients

SmartClient,WebClient,NGClient

Sample

```
var leftAlignedLabel = form.newLabel('LEFT', 10, 10, 300, 20);  
leftAlignedLabel.horizontalAlignment = SM_ALIGNMENT.LEFT;
```

RIGHT

Constant used for setting horizontal alignment for components.
It makes the text inside the component be right aligned vertically.

Returns

[Number](#)

Supported Clients

SmartClient,WebClient,NGClient

Sample

```
var rightAlignedLabel = form.newLabel('RIGHT', 10, 70, 300, 20);  
rightAlignedLabel.horizontalAlignment = SM_ALIGNMENT.RIGHT;
```

TOP

Constant used for setting vertical alignment for components.
It makes the text inside the component be top aligned vertically.

Returns

[Number](#)

Supported Clients

SmartClient,WebClient,NGClient

Sample

```
var topAlignedLabel = form.newLabel('TOP', 400, 10, 50, 300);  
topAlignedLabel.verticalAlignment = SM_ALIGNMENT.TOP;
```