

ColumnInfo

 Apr 06, 2024 15:09

Supported Clients

SmartClient WebClient NGClient MobileClient

Property Summary		
Number	autoEnterSubType	The subtype of autoenter configured for the column.
Number	autoEnterType	The type of autoenter configured for the column.
String	converterName	The name of the converter used for this column.
String	converterProperties	The properties of the converter used for this column.
String	databaseDefaultValue	The database default value that is used when autoenter is set to database default.
String	databaseSequenceName	The database sequence name that is used when autoenter is set to sequence and autoenter subtype is set to database sequence.
String	defaultFormat	The default format of the column.
String	defaultValue	The value that is used when autoenter is set to custom value.
String	description	The description of the column.
String	foreignType	The foreign type of the column.
String	lookupValue	The lookup value that is used when autotype is set to lookup.
String	titleText	The title of the column.
String	validatorName	The name of the validator used for the column.
String	validatorProperties	The properties of the validator used for the column.

Property Details

autoEnterSubType

The subtype of autoenter configured for the column. The available options depend on the type of autoenter.

If autoenter is set to system value, then the subtype can be one of: none, creation datetime, creation username, modification datetime, modification username, database managed, creation user uid, modification user uid, creation server datetime or modification server datetime.

If autoenter is set to sequence, then the subtype can be one of: none, Servoy sequence, database sequence, database identity or universally unique identifier.

Returns

[Number](#)

Supported Clients

SmartClient,WebClient,NGClient,MobileClient

Sample

autoEnterType

The type of autoenter configured for the column. Can be one of: none, system value, sequence, custom value or lookup value.

Returns

[Number](#)

Supported Clients

SmartClient,WebClient,NGClient,MobileClient

Sample

converterName

The name of the converter used for this column.

Returns

[String](#)

Supported Clients

SmartClient,WebClient,NGClient,MobileClient

Sample**converterProperties**

The properties of the converter used for this column.

Returns

[String](#)

Supported Clients

SmartClient,WebClient,NGClient,MobileClient

Sample**databaseDefaultValue**

The database default value that is used when autoenter is set to database default.

Returns

[String](#)

Supported Clients

SmartClient,WebClient,NGClient,MobileClient

Sample**databaseSequenceName**

The database sequence name that is used when autoenter is set to sequence and autoenter subtype is set to database sequence.

Returns

[String](#)

Supported Clients

SmartClient,WebClient,NGClient,MobileClient

Sample**defaultFormat**

The default format of the column.
Currently only strings or numbers are supported.

Returns

[String](#)

Supported Clients

SmartClient,WebClient,NGClient,MobileClient

Sample**defaultValue**

The value that is used when autoenter is set to custom value.

Returns

[String](#)

Supported Clients

SmartClient,WebClient,NGClient,MobileClient

Sample**description**

The description of the column.

Returns

[String](#)

Supported Clients

SmartClient,WebClient,NGClient,MobileClient

Sample**foreignType**

The foreign type of the column. It is used for foreign key columns, to hold the foreign table they point to.

Returns

[String](#)

Supported Clients

SmartClient,WebClient,NGClient,MobileClient

Sample**lookupValue**

The lookup value that is used when autotype is set to lookup.

Returns

[String](#)

Supported Clients

SmartClient,WebClient,NGClient,MobileClient

Sample**titleText**

The title of the column.

Returns

[String](#)

Supported Clients

SmartClient,WebClient,NGClient,MobileClient

Sample**validatorName**

The name of the validator used for the column.

Returns

[String](#)

Supported Clients

SmartClient,WebClient,NGClient,MobileClient

Sample**validatorProperties**

The properties of the validator used for the column.

Returns

[String](#)

Supported Clients

SmartClient,WebClient,NGClient,MobileClient

Sample