

# ALIGNMENT

 Apr 12, 2024 07:36

Supported Clients

SmartClient WebClient NGClient

| Constants Summary |         |                                                                             |
|-------------------|---------|-----------------------------------------------------------------------------|
| Number            | BOTTOM  | Constant used for setting vertical alignment for components.                |
| Number            | CENTER  | Constant used for setting horizontal and vertical alignment for components. |
| Number            | DEFAULT | Constant used for setting horizontal and vertical alignment.                |
| Number            | LEFT    | Constant used for setting horizontal alignment for components.              |
| Number            | RIGHT   | Constant used for setting horizontal alignment for components.              |
| Number            | TOP     | Constant used for setting vertical alignment for components.                |

## Constants Details

**BOTTOM**  
Constant used for setting vertical alignment for components.  
It makes the text inside the component be bottom aligned vertically.

Returns

Number

Supported Clients  
SmartClient,WebClient,NGClient  
Sample

```
var bottomAlignedLabel = form.newLabel('BOTTOM', 520, 10, 50, 300);
bottomAlignedLabel.verticalAlignment = SM_ALIGNMENT.BOTTOM;
```

**CENTER**  
Constant used for setting horizontal and vertical alignment for components. If used for horizontal alignment, then the text of the component will be horizontally centered. Similarly, if used for vertical alignment, then the text of the component will be vertically centered.

Returns

Number

Supported Clients  
SmartClient,WebClient,NGClient  
Sample

```
var hCenteredLabel = form.newLabel('CENTER', 10, 40, 300, 20);
hCenteredLabel.horizontalAlignment = SM_ALIGNMENT.CENTER;
var vCenterAlignedLabel = form.newLabel('CENTER', 460, 10, 50, 300);
vCenterAlignedLabel.verticalAlignment = SM_ALIGNMENT.CENTER
```

**DEFAULT**  
Constant used for setting horizontal and vertical alignment. DEFAULT value makes the alignment behave as if it was not changed before.

Returns

Number

Supported Clients  
SmartClient,WebClient,NGClient

---

**Sample**

```
var hLabel = myJSForm.getLabel('label_name');  
if (hLabel.horizontalAlignment == SM_ALIGNMENT.LEFT) hLabel.horizontalAlignment = SM_ALIGNMENT.DEFAULT;
```

**LEFT**

Constant used for setting horizontal alignment for components.  
It makes the text inside the component be left aligned horizontally.

**Returns**

[Number](#)

**Supported Clients**

SmartClient,WebClient,NGClient

**Sample**

```
var leftAlignedLabel = form.newLabel('LEFT', 10, 10, 300, 20);  
leftAlignedLabel.horizontalAlignment = SM_ALIGNMENT.LEFT;
```

**RIGHT**

Constant used for setting horizontal alignment for components.  
It makes the text inside the component be right aligned vertically.

**Returns**

[Number](#)

**Supported Clients**

SmartClient,WebClient,NGClient

**Sample**

```
var rightAlignedLabel = form.newLabel('RIGHT', 10, 70, 300, 20);  
rightAlignedLabel.horizontalAlignment = SM_ALIGNMENT.RIGHT;
```

**TOP**

Constant used for setting vertical alignment for components.  
It makes the text inside the component be top aligned vertically.

**Returns**

[Number](#)

**Supported Clients**

SmartClient,WebClient,NGClient

**Sample**

```
var topAlignedLabel = form.newLabel('TOP', 400, 10, 50, 300);  
topAlignedLabel.verticalAlignment = SM_ALIGNMENT.TOP;
```