


CustomApiBuilder

 Apr 14, 2024 11:45

Supported Clients

NGClient

Methods Summary

CustomApiBuilder withAccessTokenExtractor (accessTokenExtractor)	Configures the api with a token extractor which parses the concrete type of token from the response string.
CustomApiBuilder withAccessTokenMethod (tokenRequestMethod)	The request method used for the access token endpoint (defaults to POST).
CustomApiBuilder withClientAuthentication(clientAuthentication)	Configures the api with a client authentication method which specifies how the client credentials are sent.
CustomApiBuilder withRefreshTokenEndpoint (refreshTokenEndpoint)	Configure the api with the URL that receives the refresh token requests.
CustomApiBuilder withRevokeTokenEndpoint (revokeTokenEndpoint)	Configure the api with the URL that receives the revoke token requests.

Methods Details

withAccessTokenExtractor(accessTokenExtractor)

Configures the api with a token extractor which parses the concrete type of token from the response string.

Parameters

[String](#) accessTokenExtractor see plugins.oauth.OAuthTokenExtractors

Returns

[CustomApiBuilder](#) the api builder for method chaining

Supported Clients

NGClient

Sample

withAccessTokenMethod(tokenRequestMethod)

The request method used for the access token endpoint (defaults to POST).

Parameters

[String](#) tokenRequestMethod can be 'post' or 'get'

Returns

[CustomApiBuilder](#) the api builder for method chaining

Supported Clients

NGClient

Sample

withClientAuthentication(clientAuthentication)

Configures the api with a client authentication method which specifies how the client credentials are sent. They can be sent as basic Auth header or in the request body.

Parameters

[String](#) clientAuthentication see plugins.oauth.ClientAuthentication

Returns

[CustomApiBuilder](#) the api builder for method chaining

Supported Clients

NGClient

Sample

withRefreshTokenEndpoint(refreshTokenEndpoint)

Configure the api with the URL that receives the refresh token requests.

Parameters

[String](#) refreshTokenEndpoint;

Returns

[CustomApiBuilder](#) the api builder for method chaining

Supported Clients

NGClient

Sample**withRevokeTokenEndpoint(revokeTokenEndpoint)**

Configure the api with the URL that receives the revoke token requests.

Parameters

[String](#) revokeTokenEndpoint;

Returns

[CustomApiBuilder](#) the api builder for method chaining

Supported Clients

NGClient

Sample