

ALIGNMENT

Constants Summary

- Number** [#BOTTOM](#)
Constant used for setting vertical alignment for components.
- Number** [#CENTER](#)
Constant used for setting horizontal and vertical alignment for components.
- Number** [#LEFT](#)
Constant used for setting horizontal alignment for components.
- Number** [#RIGHT](#)
Constant used for setting horizontal alignment for components.
- Number** [#SPLIT_HORIZONTAL](#)
Constant used for creating horizontal split pane from tab panel, by setting its `tabOrientation`.
- Number** [#SPLIT_VERTICAL](#)
Constant used for creating vertical split pane from tab panel, by setting its `tabOrientation`.
- Number** [#TOP](#)
Constant used for setting vertical alignment for components.

Constants Details

BOTTOM

Constant used for setting vertical alignment for components.
It makes the text inside the component be bottom aligned vertically.

Returns

Number

Sample

```
var bottomAlignedLabel = form.newLabel('BOTTOM', 520, 10, 50, 300);
bottomAlignedLabel.verticalAlignment = SM_ALIGNMENT.BOTTOM;
```

CENTER

Constant used for setting horizontal and vertical alignment for components. If used for horizontal alignment, then the text of the component will be horizontally centered. Similarly, if used for vertical alignment, then the text of the component will be vertically centered.

Returns

Number

Sample

```
var hCenteredLabel = form.newLabel('CENTER', 10, 40, 300, 20);
hCenteredLabel.horizontalAlignment = SM_ALIGNMENT.CENTER;
var vCenterAlignedLabel = form.newLabel('CENTER', 460, 10, 50, 300);
vCenterAlignedLabel.verticalAlignment = SM_ALIGNMENT.CENTER;
```

LEFT

Constant used for setting horizontal alignment for components.
It makes the text inside the component be left aligned horizontally.

Returns

Number

Sample

```
var leftAlignedLabel = form.newLabel('LEFT', 10, 10, 300, 20);
leftAlignedLabel.horizontalAlignment = SM_ALIGNMENT.LEFT;
```

RIGHT

Constant used for setting horizontal alignment for components.
It makes the text inside the component be right aligned vertically.

Returns

Number

Sample

```
var rightAlignedLabel = form.newLabel('RIGHT', 10, 70, 300, 20);
rightAlignedLabel.horizontalAlignment = SM_ALIGNMENT.RIGHT;
```

SPLIT_HORIZONTAL

Constant used for creating horizontal split pane from tab panel, by setting its tabOrientation.

Returns

[Number](#)

Sample

```
var splitPane = myForm.newTabPanel('splitPane', 10, 10, 620, 460);
splitPane.tabOrientation = SM_ALIGNMENT.SPLIT_HORIZONTAL;
```

SPLIT_VERTICAL

Constant used for creating vertical split pane from tab panel, by setting its tabOrientation.

Returns

[Number](#)

Sample

```
var splitPane = myForm.newTabPanel('splitPane', 10, 10, 620, 460);
splitPane.tabOrientation = SM_ALIGNMENT.SPLIT_VERTICAL;
```

TOP

Constant used for setting vertical alignment for components.

It makes the text inside the component be top aligned vertically.

Returns

[Number](#)

Sample

```
var topAlignedLabel = form.newLabel('TOP', 400, 10, 50, 300);
topAlignedLabel.verticalAlignment = SM_ALIGNMENT.TOP;
```