

ColumnInfo

Property Summary

Number	autoEnterSubType The subtype of autoenter configured for the column.
Number	autoEnterType The type of autoenter configured for the column.
String	converterName The name of the converter used for this column.
String	converterProperties The properties of the converter used for this column.
String	databaseDefaultValue The database default value that is used when autoenter is set to database default.
String	databaseSequenceName The database sequence name that is used when autoenter is set to sequence and autoenter subtype is set to database sequence.
String	defaultFormat The default format of the column.
String	defaultValue The value that is used when autoenter is set to custom value.
String	description The description of the column.
String	foreignType The foreign type of the column.
String	lookupValue The lookup value that is used when autotype is set to lookup.
String	titleText The title of the column.
String	validatorName The name of the validator used for the column.
String	validatorProperties The properties of the validator used for the column.

Property Details

autoEnterSubType

The subtype of autoenter configured for the column. The available options depend on the type of autoenter.

If autoenter is set to system value, then the subtype can be one of: none, creation datetime, creation username, modification datetime, modification username, database managed, creation user uid, modification user uid, creation server datetime or modification server datetime.

If autoenter is set to sequence, then the subtype can be one of: none, Servoy sequence, database sequence, database identity or universally unique identifier.

Returns

[Number](#)

autoEnterType

The type of autoenter configured for the column. Can be one of: none, system value, sequence, custom value or lookup value.

Returns

[Number](#)

converterName

The name of the converter used for this column.

Returns

[String](#)

converterProperties

The properties of the converter used for this column.

Returns

[String](#)

databaseDefaultValue

The database default value that is used when autoenter is set to database default.

Returns

String

databaseSequenceName

The database sequence name that is used when autoenter is set to sequence and autoenter subtype is set to database sequence.

Returns

String

defaultFormat

The default format of the column.
Currently only strings or numbers are supported.

Returns

String

defaultValue

The value that is used when autoenter is set to custom value.

Returns

String

description

The description of the column.

Returns

String

foreignType

The foreign type of the column. It is used for foreign key columns, to hold the foreign table they point to.

Returns

String

lookupValue

The lookup value that is used when autotype is set to lookup.

Returns

String

titleText

The title of the column.

Returns

String

validatorName

The name of the validator used for the column.

Returns

String

validatorProperties

The properties of the validator used for the column.

Returns

String