

ALIGNMENT

Constants Summary

Number	BOTTOM Constant used for setting vertical alignment for components.
Number	CENTER Constant used for setting horizontal and vertical alignment for components.
Number	DEFAULT Constant used for setting horizontal and vertical alignment.
Number	LEFT Constant used for setting horizontal alignment for components.
Number	RIGHT Constant used for setting horizontal alignment for components.
Number	TOP Constant used for setting vertical alignment for components.

Constants Details

BOTTOM

Constant used for setting vertical alignment for components.
It makes the text inside the component be bottom aligned vertically.

Returns

Number

Sample

```
var bottomAlignedLabel = form.newLabel('BOTTOM', 520, 10, 50, 300);  
bottomAlignedLabel.verticalAlignment = SM_ALIGNMENT.BOTTOM;
```

CENTER

Constant used for setting horizontal and vertical alignment for components. If used for horizontal alignment, then the text of the component will be horizontally centered. Similarly, if used for vertical alignment, then the text of the component will be vertically centered.

Returns

Number

Sample

```
var hCenteredLabel = form.newLabel('CENTER', 10, 40, 300, 20);  
hCenteredLabel.horizontalAlignment = SM_ALIGNMENT.CENTER;  
var vCenterAlignedLabel = form.newLabel('CENTER', 460, 10, 50, 300);  
vCenterAlignedLabel.verticalAlignment = SM_ALIGNMENT.CENTER
```

DEFAULT

Constant used for setting horizontal and vertical alignment. DEFAULT value makes the alignment behave as if it was not changed before.

Returns

Number

Sample

```
var hLabel = myJSForm.getLabel('label_name');  
if (hLabel.horizontalAlignment == SM_ALIGNMENT.LEFT) hLabel.horizontalAlignment = SM_ALIGNMENT.DEFAULT;
```

LEFT

Constant used for setting horizontal alignment for components.
It makes the text inside the component be left aligned horizontally.

Returns[Number](#)**Sample**

```
var leftAlignedLabel = form.newLabel('LEFT', 10, 10, 300, 20);  
leftAlignedLabel.horizontalAlignment = SM_ALIGNMENT.LEFT;
```

RIGHT

Constant used for setting horizontal alignment for components.
It makes the text inside the component be right aligned vertically.

Returns[Number](#)**Sample**

```
var rightAlignedLabel = form.newLabel('RIGHT', 10, 70, 300, 20);  
rightAlignedLabel.horizontalAlignment = SM_ALIGNMENT.RIGHT;
```

TOP

Constant used for setting vertical alignment for components.
It makes the text inside the component be top aligned vertically.

Returns[Number](#)**Sample**

```
var topAlignedLabel = form.newLabel('TOP', 400, 10, 50, 300);  
topAlignedLabel.verticalAlignment = SM_ALIGNMENT.TOP;
```