

JSPart

Constants Summary

Number	BODY Constant use for specifying the type of form parts.
Number	FOOTER Constant use for specifying the type of form parts.
Number	HEADER Constant use for specifying the type of form parts.
Number	LEADING_GRAND_SUMMARY Constant use for specifying the type of form parts.
Number	LEADING_SUBSUMMARY Constant use for specifying the type of form parts.
Number	TITLE_FOOTER Constant use for specifying the type of form parts.
Number	TITLE_HEADER Constant use for specifying the type of form parts.
Number	TRAILING_GRAND_SUMMARY Constant use for specifying the type of form parts.
Number	TRAILING_SUBSUMMARY Constant use for specifying the type of form parts.

Property Summary

Boolean	allowBreakAcrossPageBounds When set, the remainder of a selected part that does not fit on the page currently being printed, will not be transported to the next page - it will break where the page ends and continue on the next page.
String	background The background color of the form part.
Boolean	discardRemainderAfterBreak When set, the remainder of a selected part that is broken due to the page ending will not be printed on the next page - it will be discarded.
String	groupByDataProviderIds For Leading Subsummary or Trailing Subsummary parts, one or more dataproviders can be added as Break (GroupBy) dataproviders.
Number	height The height of a selected part; specified in pixels.
Number	pageBreakAfterOccurrence A page break will be inserted after a specified number of occurrences of a selected part.
Boolean	pageBreakBefore When set, a page break will be inserted before each occurrence of a selected part.
Boolean	restartPageNumber When set, page numbering will be restarted after each occurrence of a selected part.
Boolean	sinkWhenLast When set, the last part on a page (such as a Trailing Grand Summary part) will "sink" to the lowest part of the page when there is free space.
String	styleClass The Cascading Style Sheet (CSS) class name applied to the part.

Method Summary

Number	getPartType() The type of this part.
Number	getPartYOffset() The Y offset of the part on the form, this will include all the super forms parts if this form extends a form.
UUID	getUUID() Returns the UUID of this component.

Constants Details

BODY

Constant use for specifying the type of form parts.

This is the default part that is repeated for each record (being displayed and/or printed).

Returns

[Number](#)

Sample

```
var body = form.newPart(JSPart.BODY, 320);
```

FOOTER

Constant use for specifying the type of form parts.

A footer is displayed at the bottom of each page when printed and can contain summaries of the current selection of records. In List view, the footer is displayed at the bottom of the list of records.

Returns

[Number](#)

Sample

```
var footer = form.newPart(JSPart.FOOTER, 440);
```

HEADER

Constant use for specifying the type of form parts.

A header is displayed at the top of each page when printed and can contain summaries of the current selection of records. In List view the header is displayed above the list of records.

Returns

[Number](#)

Sample

```
var header = form.newPart(JSPart.HEADER, 80);
```

LEADING_GRAND_SUMMARY

Constant use for specifying the type of form parts.

A Leading Grand Summary can be placed before the body part. It can contain summary fields that will generate summaries for the entire foundset.

Returns

[Number](#)

Sample

```
var leadingGrandSummary = form.newPart(JSPart.LEADING_GRAND_SUMMARY, 120);
```

LEADING_SUBSUMMARY

Constant use for specifying the type of form parts.

A Leading Subsummary can be placed before the body part. There can be multiple Leading Subsummaries per form. Each Subsummary part has a set of Group By fields which are used to group data together. Each Subsummary part can contain summary fields, which will be printed once for each group of data.

Returns

[Number](#)

Sample

```
var leadingSubsummary = form.newPart(JSPart.LEADING_SUBSUMMARY, 160);
```

TITLE_FOOTER

Constant use for specifying the type of form parts.

Appears once on the first page of a printed report. If a Footer is available, it is replaced by the Title Footer on the first page.

Returns

[Number](#)

Sample

```
var titleFooter = form.newPart(JSPart.TITLE_FOOTER, 500);
```

TITLE_HEADER

Constant use for specifying the type of form parts.

Appears only once on the first page of a printed report or on top of the first screen of a foundset. If a Header is available it is replaced by the Title Header on the first page.

Returns

[Number](#)

Sample

```
var titleHeader = form.newPart(JSPart.TITLE_HEADER, 40);
```

TRAILING_GRAND_SUMMARY

Constant use for specifying the type of form parts.

A Trailing Grand Summary can be placed after the body part. It can contain summary fields that will generate summaries for the entire foundset.

Returns

[Number](#)

Sample

```
var trailingGrandSummary = form.newPart(JSPart.TRAILING_GRAND_SUMMARY, 400);
```

TRAILING_SUBSUMMARY

Constant use for specifying the type of form parts.

A Trailing Subsummary can be placed before the body part. There can be multiple Trailing Subsummaries per form. Each Subsummary part has a set of Group By fields which are used to group data together. Each Subsummary part can contain summary fields, which will be printed once for each group of data.

Returns

[Number](#)

Sample

```
var trailingSubsummary = form.newPart(JSPart.TRAILING_SUBSUMMARY, 360);
```

Property Details

allowBreakAcrossPageBounds

When set, the remainder of a selected part that does not fit on the page currently being printed, will not be transported to the next page - it will break where the page ends and continue on the next page.

NOTE: Make sure to set this option when you are printing more than one page per record.

Returns

[Boolean](#)

Sample

```
var body = form.newPart(JSPart.BODY, 320);
body.allowBreakAcrossPageBounds = true;
body.discardRemainderAfterBreak = true;
```

background

The background color of the form part.

NOTE: When no background color has been set, the default background color will be determined by the Look and Feel (LAF) that has been selected in Application Preferences.

Returns

[String](#)

Sample

```
var body = form.newPart(JSPart.BODY, 320);
body.background = 'green';
```

discardRemainderAfterBreak

When set, the remainder of a selected part that is broken due to the page ending will not be printed on the next page - it will be discarded.

Returns

[Boolean](#)

Sample

```
var body = form.newPart(JSPart.BODY, 320);
body.allowBreakAcrossPageBounds = true;
body.discardRemainderAfterBreak = true;
```

groupbyDataProviderIDs

For Leading Subsummary or Trailing Subsummary parts, one or more dataproviders can be added as Break (GroupBy) dataproviders. The Leading/Trailing Subsummary parts will be displayed once for each resulted group of data.

Returns

[String](#)

Sample

```
var leadingSubsummary = form.newPart(JSPart.LEADING_SUBSUMMARY, 160);
leadingSubsummary.groupbyDataProviderIDs = 'my_table_text';
```

height

The height of a selected part; specified in pixels.

This height property is the lowerbound as its ending Y value (0 == top of the form).

Returns

[Number](#)

Sample

```
var part = form.newPart(JSPart.HEADER, 100);
part.height = 200;
```

pageBreakAfterOccurrence

A page break will be inserted after a specified number of occurrences of a selected part.

Returns

[Number](#)

Sample

```
var body = form.newPart(JSPart.BODY, 320);
body.pageBreakAfterOccurrence = 2;
```

pageBreakBefore

When set, a page break will be inserted before each occurrence of a selected part.

Returns

Boolean

Sample

```
var leadingSubsummary = form.newPart(JSPart.LEADING_SUBSUMMARY, 160);
leadingSubsummary.groupbyDataProviderIDs = 'my_table_text';
leadingSubsummary.pageBreakBefore = true;
```

restartPageNumber

When set, page numbering will be restarted after each occurrence of a selected part.

Returns

Boolean

Sample

```
var trailingSubsummary = form.newPart(JSPart.TRAILING_SUBSUMMARY, 360);
trailingSubsummary.groupbyDataProviderIDs = 'my_table_text';
trailingSubsummary.restartPageNumber = true;
```

sinkWhenLast

When set, the last part on a page (such as a Trailing Grand Summary part) will "sink" to the lowest part of the page when there is free space.

Returns

Boolean

Sample

```
var trailingGrandSummary = form.newPart(JSPart.TRAILING_GRAND_SUMMARY, 400);
trailingGrandSummary.sinkWhenLast = true;
```

styleClass

The Cascading Style Sheet (CSS) class name applied to the part.

Returns

String

Sample

```
var body = form.newPart(JSPart.BODY, 320);
body.styleClass = 'myBody';
```

Method Details**getPartType**

Number **getPartType** ()

The type of this part.

Returns

Number - A number representing the type of the form part.

Sample

```
var allParts = form.getParts()
for (var i=0; i<allParts.length; i++) {
    if (allParts[i].getPartType() == JSPart.BODY)
        application.output('body Y offset: ' + allParts[i].getPartYOffset());
}
```

getPartYOffset**Number** **getPartYOffset ()**

The Y offset of the part on the form, this will include all the super forms parts if this form extends a form.

Returns

Number - A number holding the Y offset of the form part.

Sample

```
var allParts = form.getParts()
for (var i=0; i<allParts.length; i++) {
    if (allParts[i].getPartType() == JSPart.BODY)
        application.output('body Y offset: ' + allParts[i].getPartYOffset());
}
```

getUUID**UUID** **getUUID ()**

Returns the UUID of this component.

Returns

UUID

Sample

```
var button_uuid = solutionModel.getForm("my_form").getButton("my_button").getUUID();
application.output(button_uuid.toString());
```